







pigpio pigpio C I/F pigpiod

# **Python Interface**

pigpiod C I/F Python

pigs

piscope

Misc

**Examples** 

Download **FAQ** 

Site Map

pigpio is a Python module for the Raspberry which talks to the pigpio daemon to allow control of the general purpose input outputs (GPIO).

### **Features**

- o the pigpio Python module can run on Windows, Macs, or Linux
- o controls one or more Pi's
- o hardware timed PWM on any of GPIO 0-31
- o hardware timed servo pulses on any of GPIO 0-31
- o callbacks when any of GPIO 0-31 change state
- o creating and transmitting precisely timed waveforms
- o reading/writing GPIO and setting their modes
- o wrappers for I2C, SPI, and serial links
- o creating and running scripts on the pigpio daemon

### **GPIO**

ALL GPIO are identified by their Broadcom number.

### **Notes**

Transmitted waveforms are accurate to a microsecond.

Callback level changes are time-stamped and will be accurate to within a few microseconds.

# **Settings**

A number of settings are determined when the pigpio daemon is started.

o the sample rate (1, 2, 4, 5, 8, or 10 us, default 5 us).

o the set of GPIO which may be updated (generally written to). The default set is those available on the Pi board revision.

o the available PWM frequencies (see set PWM frequency).

## **Exceptions**

By default a fatal exception is raised if you pass an invalid argument to a pigpio function.

If you wish to handle the returned status yourself you should set pigpio.exceptions to False.

You may prefer to check the returned status in only a few parts of your code. In that case do the following:

#### Example

```
pigpio.exceptions = False
# Code where you want to test the error status.
pigpio.exceptions = True
```

## **Usage**

This module uses the services of the C pigpio library. pigpio must be running on the Pi(s) whose GPIO are to be manipulated.

The normal way to start pigpio is as a daemon (during system start).

sudo pigpiod

Your Python program must import pigpio and create one or more instances of the pigpio.pi class. This class gives access to a specified Pi's GPIO.

#### Example

```
pi1 = pigpio.pi()  # pi1 accesses the local Pi's GPIO
pi2 = pigpio.pi('tom')  # pi2 accesses tom's GPIO
pi3 = pigpio.pi('dick')  # pi3 accesses dick's GPIO

pi1.write(4, 0)  # set local Pi's GPIO 4 low
pi2.write(4, 1)  # set tom's GPIO 4 to high
pi3.read(4)  # get level of dick's GPIO 4
```

The later example code snippets assume that pi is an instance of the pigpio.pi class.

# **OVERVIEW**

#### **Essential**

<u>pigpio.pi</u> Initialise Pi connection <u>stop</u> Stop a Pi connection

### **Beginner**

set\_modeSet a GPIO modeget\_modeGet a GPIO mode

set pull up down Set/clear GPIO pull up/down resistor

read Read a GPIO write Write a GPIO

set\_PWM\_dutycycleStart/stop PWM pulses on a GPIOget\_PWM\_dutycycleGet PWM dutycycle set on a GPIOset\_servo\_pulsewidthStart/Stop servo pulses on a GPIOget\_servo\_pulsewidthGet servo pulsewidth set on a GPIOcallbackCreate GPIO level change callback

wait\_for\_edge Wait for GPIO level change

Intermediate

<u>gpio\_trigger</u>
Send a trigger pulse to a GPIO

<u>set\_watchdog</u>
Set a watchdog on a GPIO

set\_PWM\_rangeConfigure PWM range of a GPIOget\_PWM\_rangeGet configured PWM range of a GPIO

set\_PWM\_frequencySet PWM frequency of a GPIOget\_PWM\_frequencyGet PWM frequency of a GPIO

read\_bank\_1Read all bank 1 GPIOread\_bank\_2Read all bank 2 GPIO

clear\_bank\_1Clear selected GPIO in bank 1clear\_bank\_2Clear selected GPIO in bank 2set\_bank\_1Set selected GPIO in bank 1set\_bank\_2Set selected GPIO in bank 2

**Advanced** 

get\_PWM\_real\_range Get underlying PWM range for a GPIO

<u>notify\_open</u> Request a notification handle

<u>notify\_begin</u> Start notifications for selected GPIO

notify pausePause notificationsnotify closeClose a notification

bb\_serial\_read\_openOpen a GPIO for bit bang serial readsbb\_serial\_readRead bit bang serial data from a GPIObb\_serial\_read\_closeClose a GPIO for bit bang serial readsbb\_serial\_invertInvert serial logic (1 invert, 0 normal)

<u>hardware\_clock</u> Start hardware clock on supported GPIO <u>hardware\_PWM</u> Start hardware PWM on supported GPIO

set\_glitch\_filterSet a glitch filter on a GPIOset\_noise\_filterSet a noise filter on a GPIOget\_pad\_strengthGets a pads drive strengthset\_pad\_strengthSets a pads drive strengthshellExecutes a shell command

**Scripts** 

store\_scriptStore a scriptrun\_scriptRun a stored scriptupdate\_scriptSet a scripts parameters

<u>script\_status</u> Get script status and parameters

stop\_scriptStop a running scriptdelete\_scriptDelete a stored script

**Waves** 

<u>wave\_clear</u>
Deletes all waveforms

<u>wave\_add\_new</u>
Starts a new waveform

wave add generic Adds a series of pulses to the waveform

wave add serial Adds serial data to the waveform

<u>wave\_create</u> Creates a waveform from added data

wave delete Deletes a waveform

<u>wave\_send\_once</u> Transmits a waveform once

<u>wave\_send\_repeat</u> Transmits a waveform repeatedly

wave\_send\_using\_mode Transmits a waveform in the chosen mode

wave chain Transmits a chain of waveforms

wave\_tx\_at
Returns the current transmitting waveform
Wave\_tx\_busy
Checks to see if a waveform has ended

wave tx stop Aborts the current waveform

<u>wave\_get\_micros</u>
Length in microseconds of the current waveform

wave get max micros Absolute maximum allowed micros

wave get pulses Length in pulses of the current waveform

<u>wave\_get\_max\_pulses</u> Absolute maximum allowed pulses <u>wave\_get\_cbs</u> Length in cbs of the current waveform

wave get max cbs Absolute maximum allowed cbs

I2C

i2c write device

<u>i2c\_open</u> Opens an I2C device <u>i2c\_close</u> Closes an I2C device

SMBus write quick <u>i2c write quick</u> i2c write byte SMBus write byte <u>i2c\_read\_byte</u> SMBus read byte i2c write byte data SMBus write byte data i2c write word data SMBus write word data i2c read byte data SMBus read byte data i2c read word data SMBus read word data i2c process call SMBus process call SMBus write block data i2c write block data i2c read block data SMBus read block data <u>i2c\_block\_process\_call</u> SMBus block process call i2c read i2c block data SMBus read I2C block data

<u>i2c write i2c block data</u> SMBus write I2C block data <u>i2c read device</u> Reads the raw I2C device

<u>i2c\_zip</u> Performs multiple I2C transactions

Writes the raw I2C device

bb i2c open Opens GPIO for bit banging I2C bb i2c close Closes GPIO for bit banging I2C

bb i2c zip Performs multiple bit banged I2C transactions

SPI

<u>spi\_open</u> Opens a SPI device <u>spi\_close</u> Closes a SPI device

spi\_readReads bytes from a SPI devicespi\_writeWrites bytes to a SPI devicespi\_xferTransfers bytes with a SPI devicebb\_spi\_openOpens GPIO for bit banging SPIbb\_spi\_closeCloses GPIO for bit banging SPIbb\_spi\_xferTransfers bytes with bit banging SPI

**I2C/SPI Slave** 

bsc\_xfer I2C/SPI as slave transfer bsc\_i2c I2C as slave transfer

**Serial** 

<u>serial\_open</u> Opens a serial device <u>serial\_close</u> Closes a serial device

serial\_readReads bytes from a serial deviceserial\_read\_byteReads a byte from a serial device

<u>serial\_write\_byte</u>
Writes bytes to a serial device
Writes a byte to a serial device

<u>serial\_data\_available</u> Returns number of bytes ready to be read

**Files** 

<u>file\_open</u> Opens a file <u>file\_close</u> Closes a file

file\_readReads bytes from a filefile\_writeWrites bytes to a file

file\_seekSeeks to a position within a filefile\_listList files which match a pattern

**Events** 

<u>event\_callback</u> Sets a callback for an event

event\_triggerTriggers an eventwait\_for\_eventWait for an event

Custom

<u>custom\_1</u><u>custom\_2</u>User custom function 1<u>ustom\_2</u>

Utility

<u>get current tick</u> Get current tick (microseconds)

get\_hardware\_revision Get hardware revision get\_pigpio\_version Get the pigpio version

<u>pigpio.error\_text</u> Gets error text from error number <u>pigpio.tickDiff</u> Returns difference between two ticks

# class pi

## pigpio.pi(host, port, show\_errors)

Grants access to a Pi's GPIO.

#### **Parameters**

```
host:= the host name of the Pi on which the pigpio daemon is running. The default is localhost unless overridden by the PIGPIO_ADDR environment variable.

port:= the port number on which the pigpio daemon is listening.
    The default is 8888 unless overridden by the PIGPIO_PORT environment variable. The pigpio daemon must have been started with the same port number.
```

This connects to the pigpio daemon and reserves resources to be used for sending commands and receiving notifications.

An instance attribute <u>connected</u> may be used to check the success of the connection. If the connection is established successfully <u>connected</u> will be True, otherwise False.

#### Example

```
pi = pigio.pi()  # use defaults
pi = pigpio.pi('mypi')  # specify host, default port
pi = pigpio.pi('mypi', 7777) # specify host and port

pi = pigpio.pi()  # exit script if no connection
if not pi.connected:
    exit()
```

# bb\_i2c\_close(SDA)

This function stops bit banging I2C on a pair of GPIO previously opened with bb i2c open.

#### **Parameters**

```
SDA:= 0-31, the SDA GPIO used in a prior call to bb i2c open
```

Returns 0 if OK, otherwise PI BAD USER GPIO, or PI NOT I2C GPIO.

#### Example

```
pi.bb_i2c_close(SDA)
```

# bb\_i2c\_open(SDA, SCL, baud)

This function selects a pair of GPIO for bit banging I2C at a specified baud rate.

Bit banging I2C allows for certain operations which are not possible with the standard I2C driver.

```
o baud rates as low as 50
o repeated starts
o clock stretching
o I2C on any pair of spare GPIO
```

#### **Parameters**

```
SDA:= 0-31
SCL:= 0-31
baud:= 50-500000
```

Returns 0 if OK, otherwise PI\_BAD\_USER\_GPIO, PI\_BAD\_I2C\_BAUD, or PI\_GPIO\_IN\_USE.

### NOTE:

The GPIO used for SDA and SCL must have pull-ups to 3V3 connected. As a guide the hardware pull-ups on pins 3 and 5 are 1k8 in value.

#### Example

```
h = pi.bb i2c open(4, 5, 50000) # bit bang on GPIO 4/5 at 50kbps
```

## bb\_i2c\_zip(SDA, data)

This function executes a sequence of bit banged I2C operations. The operations to be performed are specified by the contents of data which contains the concatenated command codes and associated data.

#### **Parameters**

```
SDA:= 0-31 (as used in a prior call to <a href="mailto:bb_i2c_open">bb_i2c_open</a>) data:= the concatenated I2C commands, see below
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

#### Example

```
(count, data) = pi.bb_i2c_zip(
SDA, [4, 0x53, 2, 7, 1, 0x32, 2, 6, 6, 3, 0])
```

The following command codes are supported:

| Name    | Cmd & Data | Meaning                           |
|---------|------------|-----------------------------------|
| End     | 0          | No more commands                  |
| Escape  | 1          | Next P is two bytes               |
| Start   | 2          | Start condition                   |
| Stop    | 3          | Stop condition                    |
| Address | 4 P        | Set I2C address to P              |
| Flags   | 5 lsb msb  | Set I2C flags to lsb + (msb << 8) |
| Read    | 6 P        | Read P bytes of data              |
| Write   | 7 P        | Write P bytes of data             |

The address, read, and write commands take a parameter P. Normally P is one byte (0-255). If the command is preceded by the Escape command then P is two bytes (0-65535, least significant byte first).

The address and flags default to 0. The address and flags maintain their previous value until updated.

No flags are currently defined.

Any read I2C data is concatenated in the returned bytearray.

#### **Example**

```
Set address 0x53
start, write 0x32, (re)start, read 6 bytes, stop
Set address 0x1E
start, write 0x03, (re)start, read 6 bytes, stop
Set address 0x68
start, write 0x1B, (re)start, read 8 bytes, stop
End

0x04 0x53
0x02 0x07 0x01 0x32 0x02 0x06 0x06 0x03

0x04 0x1E
0x02 0x07 0x01 0x03 0x02 0x06 0x06 0x03

0x04 0x68
0x02 0x07 0x01 0x1B 0x02 0x06 0x08 0x03

0x00
```

## bb serial invert(user\_gpio, invert)

Invert serial logic.

#### **Parameters**

```
user_gpio:= 0-31 (opened in a prior call to bb_serial read_open)
invert:= 0-1 (1 invert, 0 normal)
```

#### Example

```
status = pi.bb serial invert(17, 1)
```

# bb\_serial\_read(user\_gpio)

Returns data from the bit bang serial cyclic buffer.

#### **Parameters**

```
user_gpio:= 0-31 (opened in a prior call to <a href="mailto:bb_serial_read_open">bb_serial_read_open</a>)
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

The bytes returned for each character depend upon the number of data bits <u>bb\_bits</u> specified in the <u>bb\_serial\_read\_open</u> command.

```
For <u>bb_bits</u> 1-8 there will be one byte per character.
For <u>bb_bits</u> 9-16 there will be two bytes per character.
For <u>bb_bits</u> 17-32 there will be four bytes per character.
```

```
(count, data) = pi.bb serial read(4)
```

## bb serial read close(user gpio)

Closes a GPIO for bit bang reading of serial data.

#### **Parameters**

```
user_gpio:= 0-31 (opened in a prior call to <a href="mailto:bb_serial_read_open">bb_serial_read_open</a>)
```

#### Example

```
status = pi.bb_serial_read_close(17)
```

## bb\_serial\_read\_open(<u>user\_gpio</u>, <u>baud</u>, <u>bb\_bits</u>)

Opens a GPIO for bit bang reading of serial data.

#### **Parameters**

```
user_gpio:= 0-31, the GPIO to use.
   baud:= 50-250000, the baud rate.
bb_bits:= 1-32, the number of bits per word, default 8.
```

The serial data is held in a cyclic buffer and is read using bb\_serial\_read.

It is the caller's responsibility to read data from the cyclic buffer in a timely fashion.

### Example

```
status = pi.bb_serial_read_open(4, 19200)
status = pi.bb_serial_read_open(17, 9600)
```

# bb\_spi\_close(CS)

This function stops bit banging SPI on a set of GPIO opened with bb spi open.

#### **Parameters**

```
CS:= 0-31, the CS GPIO used in a prior call to <a href="bb spi open">bb spi open</a>
```

Returns 0 if OK, otherwise PI\_BAD\_USER\_GPIO, or PI\_NOT\_SPI\_GPIO.

#### **Example**

```
pi.bb spi close(CS)
```

# bb\_spi\_open(CS, MISO, MOSI, SCLK, baud, spi\_flags)

This function selects a set of GPIO for bit banging SPI at a specified baud rate.

### **Parameters**

```
CS := 0-31

MISO := 0-31

MOSI := 0-31

SCLK := 0-31

baud := 50-250000

spiFlags := see below
```

spiFlags consists of the least significant 22 bits.

mm defines the SPI mode, defaults to 0

```
Mode CPOL CPHA

0 0 0

1 0 1

2 1 0

3 1 1
```

The following constants may be used to set the mode:

```
pigpio.SPI_MODE_0
pigpio.SPI_MODE_1
pigpio.SPI_MODE_2
pigpio.SPI_MODE_3
```

Alternatively pigpio.SPI CPOL and/or pigpio.SPI CPHA may be used.

p is 0 if CS is active low (default) and 1 for active high. pigpio.SPI\_CS\_HIGH\_ACTIVE may be used to set this flag.

T is 1 if the least significant bit is transmitted on MOSI first, the default (0) shifts the most significant bit out first. pigpio.SPI\_TX\_LSBFIRST may be used to set this flag.

R is 1 if the least significant bit is received on MISO first, the default (0) receives the most significant bit first. pigpio.SPI\_RX\_LSBFIRST may be used to set this flag.

The other bits in spiFlags should be set to zero.

```
Returns 0 if OK, otherwise PI_BAD_USER_GPIO, PI_BAD_SPI_BAUD, or PI_GPIO_IN_USE.
```

If more than one device is connected to the SPI bus (defined by SCLK, MOSI, and MISO) each must have its own CS.

### Example

```
bb_spi_open(10, MISO, MOSI, SCLK, 10000, 0); // device 1
bb_spi_open(11, MISO, MOSI, SCLK, 20000, 3); // device 2
```

# bb\_spi\_xfer(<u>CS</u>, <u>data</u>)

This function executes a bit banged SPI transfer.

#### **Parameters**

```
CS:= 0-31 (as used in a prior call to <a href="bb">bb</a> spi open) data:= data to be sent
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

```
#!/usr/bin/env python
import pigpio
CE0=5
CE1=6
MISO=13
MOSI=19
SCLK=12
pi = pigpio.pi()
if not pi.connected:
   exit()
pi.bb spi open(CEO, MISO, MOSI, SCLK, 10000, 0) # MCP4251 DAC
pi.bb spi open(CE1, MISO, MOSI, SCLK, 20000, 3) # MCP3008 ADC
for i in range (256):
   count, data = pi.bb spi xfer(CEO, [0, i]) # Set DAC value
   if count == 2:
      count, data = pi.bb spi xfer(CE0, [12, 0]) # Read back DAC
      if count == 2:
         set_val = data[1]
         count, data = pi.bb_spi_xfer(CE1, [1, 128, 0]) # Read ADC
         if count == 3:
            read_val = ((data[1]&3)<<8) | data[2]</pre>
            print("{} {}".format(set val, read val))
pi.bb spi close (CEO)
pi.bb spi close(CE1)
pi.stop()
```

# bsc\_i2c(i2c\_address, data)

This function allows the Pi to act as a slave I2C device.

The data bytes (if any) are written to the BSC transmit FIFO and the bytes in the BSC receive FIFO are returned.

### **Parameters**

The returned value is a tuple of the status, the number of bytes read, and a bytearray containing the read bytes.

See bsc xfer for details of the status value.

If there was an error the status will be less than zero (and will contain the error code).

Note that an i2c\_address of 0 may be used to close the BSC device and reassign the used GPIO (18/19) as inputs.

This example assumes GPIO 2/3 are connected to GPIO 18/19.

```
#!/usr/bin/env python
import time
import pigpio
I2C ADDR=0x13
def i2c(id, tick):
    global pi
    s, b, d = pi.bsc_i2c(I2C_ADDR)
    if b:
        if d[0] == ord('t'): # 116 send 'HH:MM:SS*'
            print("sent={} FR={} received={} [{}]".
               format(s >> 16, s \& 0 x f f f, b, d))
            s, b, d = pi.bsc_i2c(I2C_ADDR,
                "{}*".format(time.asctime()[11:19]))
        elif d[0] == ord('d'): # 100 send 'Sun Oct 30*'
            print("sent={} FR={} received={} [{}]".
               format(s >> 16, s \& 0 x f f f, b, d))
            s, b, d = pi.bsc i2c(I2C ADDR,
               "{}*".format(time.asctime()[:10]))
pi = pigpio.pi()
if not pi.connected:
    exit()
# Respond to BSC slave activity
e = pi.event callback(pigpio.EVENT BSC, i2c)
pi.bsc i2c(I2C ADDR) # Configure BSC as I2C slave
time.sleep(600)
e.cancel()
pi.bsc_i2c(0) # Disable BSC peripheral
pi.stop()
```

### While running the above.

```
$ i2cdetect -y 1
   0 1 2 3 4 5 6 7 8 9 a b c d e f
10: -- -- 13 -- -- -- -- -- -- -- --
20: -- -- -- -- -- -- -- -- --
40: -- -- -- -- -- -- -- -- --
50: -- -- -- -- -- -- -- -- --
60: -- -- -- -- -- -- -- -- --
70: -- -- -- -- -- --
$ pigs i2co 1 0x13 0
$ pigs i2cwd 0 116
$ pigs i2crd 0 9 -a
9 10:13:58*
$ pigs i2cwd 0 116
$ pigs i2crd 0 9 -a
9 10:14:29*
$ pigs i2cwd 0 100
$ pigs i2crd 0 11 -a
11 Sun Oct 30*
```

```
$ pigs i2cwd 0 100
$ pigs i2crd 0 11 -a
11 Sun Oct 30*

$ pigs i2cwd 0 116
$ pigs i2crd 0 9 -a
9 10:23:16*

$ pigs i2cwd 0 100
$ pigs i2crd 0 11 -a
11 Sun Oct 30*
```

## bsc\_xfer(bsc\_control, data)

This function provides a low-level interface to the SPI/I2C Slave peripheral. This peripheral allows the Pi to act as a slave device on an I2C or SPI bus.

I can't get SPI to work properly. I tried with a control word of 0x303 and swapped MISO and MOSI.

The function sets the BSC mode, writes any data in the transmit buffer to the BSC transmit FIFO, and copies any data in the BSC receive FIFO to the receive buffer.

#### **Parameters**

The returned value is a tuple of the status (see below), the number of bytes read, and a bytearray containing the read bytes. If there was an error the status will be less than zero (and will contain the error code).

Note that the control word sets the BSC mode. The BSC will stay in that mode until a different control word is sent.

The BSC peripheral uses GPIO 18 (SDA) and 19 (SCL) in I2C mode and GPIO 18 (MOSI), 19 (SCLK), 20 (MISO), and 21 (CE) in SPI mode. You need to swap MISO/MOSI between master and slave.

When a zero control word is received GPIO 18-21 will be reset to INPUT mode.

bsc control consists of the following bits:

```
22 21 20 19 18 17 16 15 14 13 12 11 10 9 8 7 6 5 4 3 2 1 0 a a a a a a a - - IT HC TF IR RE TE BK EC ES PL PH I2 SP EN
```

Bits 0-13 are copied unchanged to the BSC CR register. See pages 163-165 of the Broadcom peripherals document for full details.

| aaaaaaa | defines the I2C slave address (only relevant in I2C mode) |
|---------|---|
| IT      | invert transmit status flags                              |
| НС      | enable host control                                       |
| TF      | enable test FIFO  |
| IR      | invert receive status flags                               |
| RE      | enable receive  |
| TE      | enable transmit   |
| ВК      | abort operation and clear FIFOs                           |
| EC      | send control register as first I2C byte                   |
|         |   |

| ES | send status register as first I2C byte |
|----|--|
| PL | set SPI polarity high                  |
| PH | set SPI phase high                     |
| 12 | enable I2C mode                        |
| SP | enable SPI mode                        |
| EN | enable BSC peripheral                  |

The status has the following format:

```
20 19 18 17 16 15 14 13 12 11 10 9 8 7 6 5 4 3 2 1 0 S S S S R R R R R R T T T T T RB TE RF TF RE TB
```

Bits 0-15 are copied unchanged from the BSC FR register. See pages 165-166 of the Broadcom peripherals document for full details.

| SSSSS | number of bytes successfully copied to transmit FIFO |
|-------|--|
| RRRRR | number of bytes in receieve FIFO                     |
| TTTTT | number of bytes in transmit FIFO                     |
| RB    | receive busy   |
| TE    | transmit FIFO empty                                  |
| RF    | receive FIFO full                                    |
| TF    | transmit FIFO full                                   |
| RE    | receive FIFO empty                                   |
| ТВ    | transmit busy  |

### Example

```
(status, count, data) = pi.bsc_xfer(0x330305, "Hello!")
```

# callback(<u>user\_gpio</u>, <u>edge</u>, <u>func</u>)

Calls a user supplied function (a callback) whenever the specified GPIO edge is detected.

### **Parameters**

```
user_gpio:= 0-31.
    edge:= EITHER_EDGE, RISING_EDGE (default), or FALLING_EDGE.
    func:= user supplied callback function.
```

The user supplied callback receives three parameters, the GPIO, the level, and the tick.

| Parameter | Value  | Meaning   |
|-----------|--------|---|
| GPIO      | 0-31   | The GPIO which has changed state  |
| level     | 0-2    | <pre>0 = change to low (a falling edge) 1 = change to high (a rising edge) 2 = no level change (a watchdog timeout)</pre> |
| tick      | 32 bit | The number of microseconds since boot WARNING: this wraps around from 4294967295 to 0 roughly every 72 minutes            |

If a user callback is not specified a default tally callback is provided which simply counts edges. The count may be retrieved by calling the tally function. The count may be reset to zero by calling the reset tally function.

The callback may be cancelled by calling the cancel function.

A GPIO may have multiple callbacks (although I can't think of a reason to do so).

### **Example**

```
def cbf(gpio, level, tick):
    print(gpio, level, tick)

cb1 = pi.callback(22, pigpio.EITHER_EDGE, cbf)

cb2 = pi.callback(4, pigpio.EITHER_EDGE)

cb3 = pi.callback(17)

print(cb3.tally())

cb3.reset_tally()

cb1.cancel() # To cancel callback cb1.
```

## clear\_bank\_1(bits)

Clears GPIO 0-31 if the corresponding bit in bits is set.

#### **Parameters**

```
bits:= a 32 bit mask with 1 set if the corresponding GPIO is
    to be cleared.
```

A returned status of PI\_SOME\_PERMITTED indicates that the user is not allowed to write to one or more of the GPIO.

#### Example

```
pi.clear bank 1(int("111110010000",2))
```

# clear\_bank\_2(bits)

Clears GPIO 32-53 if the corresponding bit (0-21) in bits is set.

### **Parameters**

```
bits:= a 32 bit mask with 1 set if the corresponding GPIO is
    to be cleared.
```

A returned status of PI\_SOME\_PERMITTED indicates that the user is not allowed to write to one or more of the GPIO.

### **Example**

```
pi.clear_bank_2(0x1010)
```

# custom\_1(arg1, arg2, argx)

Calls a pigpio function customised by the user.

#### **Parameters**

```
arg1:= >=0, default 0.
arg2:= >=0, default 0.
argx:= extra arguments (each 0-255), default empty.
```

The returned value is an integer which by convention should be >=0 for OK and <0 for error.

### **Example**

```
value = pi.custom_1()
value = pi.custom_1(23)
value = pi.custom_1(0, 55)
value = pi.custom_1(23, 56, [1, 5, 7])
value = pi.custom_1(23, 56, b"hello")
value = pi.custom_1(23, 56, "hello")
```

## custom\_2(arg1, argx, retMax)

Calls a pigpio function customised by the user.

#### **Parameters**

```
arg1:= >=0, default 0.
argx:= extra arguments (each 0-255), default empty.
retMax:= >=0, maximum number of bytes to return, default 8192.
```

The returned value is a tuple of the number of bytes returned and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

### Example

```
(count, data) = pi.custom_2()
(count, data) = pi.custom_2(23)
(count, data) = pi.custom_2(23, [1, 5, 7])
(count, data) = pi.custom_2(23, b"hello")
(count, data) = pi.custom_2(23, "hello", 128)
```

# delete\_script(script\_id)

Deletes a stored script.

#### **Parameters**

```
script_id:= id of stored script.
```

```
status = pi.delete_script(sid)
```

## event callback(event, func)

Calls a user supplied function (a callback) whenever the specified event is signalled.

#### **Parameters**

```
event:= 0-31.
func:= user supplied callback function.
```

The user supplied callback receives two parameters, the event id, and the tick.

If a user callback is not specified a default tally callback is provided which simply counts events. The count may be retrieved by calling the tally function. The count may be reset to zero by calling the reset tally function.

The callback may be cancelled by calling the event cancel function.

An event may have multiple callbacks (although I can't think of a reason to do so).

#### Example

```
def cbf(event, tick):
    print(event, tick)

cb1 = pi.event_callback(22, cbf)

cb2 = pi.event_callback(4)

print(cb2.tally())

cb2.reset_tally()

cb1.event_cancel() # To cancel callback cb1.
```

# event trigger(event)

This function signals the occurrence of an event.

#### **Parameters**

```
event:= 0-31, the event
```

Returns 0 if OK, otherwise PI BAD EVENT ID.

An event is a signal used to inform one or more consumers to start an action. Each consumer which has registered an interest in the event (e.g. by calling <a href="mailto:event\_callback">event\_callback</a>) will be informed by a callback.

One event, EVENT\_BSC (31) is predefined. This event is auto generated on BSC slave activity.

The meaning of other events is arbitrary.

Note that other than its id and its tick there is no data associated with an event.

### Example

```
pi.event_trigger(23)
```

# file close(handle)

Closes the file associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to file_open).
```

### **Example**

```
pi.file_close(handle)
```

## file\_list(fpattern)

Returns a list of files which match a pattern.

#### **Parameters**

```
fpattern:= file pattern to match.
```

Returns the number of returned bytes if OK, otherwise PI\_NO\_FILE\_ACCESS, or PI\_NO\_FILE\_MATCH.

The pattern must match an entry in /opt/pigpio/access. The pattern may contain wildcards. See <u>file\_open</u>.

### NOTE

The returned value is not the number of files, it is the number of bytes in the buffer. The file names are separated by newline characters.

### **Example**

```
#!/usr/bin/env python
import pigpio
pi = pigpio.pi()
if not pi.connected:
    exit()

# Assumes /opt/pigpio/access contains the following line:
# /ram/*.c r

c, d = pi.file_list("/ram/p*.c")
if c > 0:
    print(d)

pi.stop()
```

# file\_open(file\_name, file\_mode)

This function returns a handle to a file opened in a specified mode.

#### **Parameters**

```
file_name:= the file to open.
file_mode:= the file open mode.
```

Returns a handle (>=0) if OK, otherwise PI\_NO\_HANDLE, PI\_NO\_FILE\_ACCESS, PI\_BAD\_FILE\_MODE, PI\_FILE\_OPEN\_FAILED, or PI\_FILE\_IS\_A\_DIR.

#### Example

#### File

A file may only be opened if permission is granted by an entry in /opt/pigpio/access. This is intended to allow remote access to files in a more or less controlled manner.

Each entry in /opt/pigpio/access takes the form of a file path which may contain wildcards followed by a single letter permission. The permission may be R for read, W for write, U for read/write, and N for no access.

Where more than one entry matches a file the most specific rule applies. If no entry matches a file then access is denied.

Suppose /opt/pigpio/access contains the following entries:

```
/home/* n
/home/pi/shared/dir_1/* w
/home/pi/shared/dir_2/* r
/home/pi/shared/dir_3/* u
/home/pi/shared/dir_1/file.txt n
```

Files may be written in directory dir 1 with the exception of file.txt.

Files may be read in directory dir 2.

Files may be read and written in directory dir\_3.

If a directory allows read, write, or read/write access then files may be created in that directory.

In an attempt to prevent risky permissions the following paths are ignored in /opt/pigpio/access:

```
a path containing ..
a path containing only wildcards (*?)
a path containing less than two non-wildcard parts
```

#### Mode

The mode may have the following values:

| Constant   | Value | Meaning                           |
|------------|-------|-----------------------------------|
| FILE_READ  | 1     | open file for reading             |
| FILE_WRITE | 2     | open file for writing             |
| FILE_RW    | 3     | open file for reading and writing |

The following values may be or'd into the mode:

| Name        | Value | Meaning                                       |
|-------------|-------|---|
| FILE_APPEND | 4     | All writes append data to the end of the file |
|             |       |   |

| FILE_CREATE | 8  | The file is created if it doesn't exist |
|-------------|----|---|
| FILE_TRUNC  | 16 | The file is truncated                   |

Newly created files are owned by root with permissions owner read and write.

### Example

```
#!/usr/bin/env python
import pigpio
pi = pigpio.pi()
if not pi.connected:
  exit()
# Assumes /opt/pigpio/access contains the following line:
# /ram/*.c r
handle = pi.file_open("/ram/pigpio.c", pigpio.FILE_READ)
done = False
while not done:
  c, d = pi.file read(handle, 60000)
   if c > 0:
     print(d)
   else:
     done = True
pi.file close(handle)
pi.stop()
```

## file\_read(handle, count)

Reads up to count bytes from the file associated with handle.

### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>file_open</u>).
count:= >0, the number of bytes to read.
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

#### Example

```
(b, d) = pi.file_read(h2, 100)
if b > 0:
    # process read data
```

# file\_seek(handle, seek\_offset, seek\_from)

Seeks to a position relative to the start, current position, or end of the file. Returns the new position.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>file_open</u>).
seek_offset:= byte offset.
seek_from:= FROM_START, FROM_CURRENT, or FROM_END.
```

#### Example

```
new_pos = pi.file_seek(h, 100, pigpio.FROM_START)
cur_pos = pi.file_seek(h, 0, pigpio.FROM_CURRENT)
file_size = pi.file_seek(h, 0, pigpio.FROM_END)
```

## file\_write(handle, data)

Writes the data bytes to the file associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>file_open</u>).
  data:= the bytes to write.
```

### Example

```
pi.file_write(h1, b'\x02\x03\x04')
pi.file_write(h2, b'help')
pi.file_write(h2, "hello")
pi.file write(h1, [2, 3, 4])
```

## get\_PWM\_dutycycle(user\_gpio)

Returns the PWM dutycycle being used on the GPIO.

#### **Parameters**

```
user gpio:= 0-31.
```

Returns the PWM dutycycle.

For normal PWM the dutycycle will be out of the defined range for the GPIO (see get PWM range).

If a hardware clock is active on the GPIO the reported dutycycle will be 500000 (500k) out of 1000000 (1M).

If hardware PWM is active on the GPIO the reported dutycycle will be out of a 1000000 (1M).

#### Example

```
pi.set_PWM_dutycycle(4, 25)
print(pi.get_PWM_dutycycle(4))
25

pi.set_PWM_dutycycle(4, 203)
print(pi.get_PWM_dutycycle(4))
203
```

# get\_PWM\_frequency(user\_gpio)

Returns the frequency of PWM being used on the GPIO.

#### **Parameters**

```
user_gpio:= 0-31.
```

Returns the frequency (in Hz) used for the GPIO.

For normal PWM the frequency will be that defined for the GPIO by <a href="mailto:set\_PWM\_frequency">set\_PWM\_frequency</a>.

If a hardware clock is active on the GPIO the reported frequency will be that set by <a href="hardware\_clock">hardware\_clock</a>.

If hardware PWM is active on the GPIO the reported frequency will be that set by hardware PWM.

#### Example

```
pi.set_PWM_frequency(4,0)
print(pi.get_PWM_frequency(4))
10
pi.set_PWM_frequency(4, 800)
print(pi.get_PWM_frequency(4))
800
```

# get\_PWM\_range(user\_gpio)

Returns the range of PWM values being used on the GPIO.

#### **Parameters**

```
user_gpio:= 0-31.
```

If a hardware clock or hardware PWM is active on the GPIO the reported range will be 1000000 (1M).

#### Example

```
pi.set_PWM_range(9, 500)
print(pi.get_PWM_range(9))
500
```

# get\_PWM\_real\_range(user\_gpio)

Returns the real (underlying) range of PWM values being used on the GPIO.

#### **Parameters**

```
user_gpio:= 0-31.
```

If a hardware clock is active on the GPIO the reported real range will be 1000000 (1M).

If hardware PWM is active on the GPIO the reported real range will be approximately 250M divided by the set PWM frequency.

```
pi.set_PWM_frequency(4, 800)
print(pi.get_PWM_real_range(4))
250
```

## get current tick()

Returns the current system tick.

Tick is the number of microseconds since system boot. As an unsigned 32 bit quantity tick wraps around approximately every 71.6 minutes.

### Example

```
t1 = pi.get_current_tick()
time.sleep(1)
t2 = pi.get current tick()
```

# get\_hardware\_revision()

Returns the Pi's hardware revision number.

The hardware revision is the last few characters on the Revision line of /proc/cpuinfo.

The revision number can be used to determine the assignment of GPIO to pins (see gpio).

There are at least three types of board.

Type 1 boards have hardware revision numbers of 2 and 3.

Type 2 boards have hardware revision numbers of 4, 5, 6, and 15.

Type 3 boards have hardware revision numbers of 16 or greater.

If the hardware revision can not be found or is not a valid hexadecimal number the function returns 0.

#### Example

```
print(pi.get_hardware_revision())
```

# get\_mode(gpio)

Returns the GPIO mode.

#### **Parameters**

```
gpio:= 0-53.
```

### Returns a value as follows

```
0 = INPUT

1 = OUTPUT

2 = ALT5

3 = ALT4

4 = ALT0

5 = ALT1

6 = ALT2

7 = ALT3
```

```
print(pi.get_mode(0))
4
```

## get pad strength(pad)

This function returns the pad drive strength in mA.

#### **Parameters**

```
pad:= 0-2, the pad to get.
```

Returns the pad drive strength if OK, otherwise PI BAD PAD.

| Pad | GPIO  |
|-----|-------|
| 0   | 0-27  |
| 1   | 28-45 |
| 2   | 46-53 |

### **Example**

```
strength = pi.get_pad_strength(0) # Get pad 0 strength.
```

# get\_pigpio\_version()

Returns the pigpio software version.

### **Example**

```
v = pi.get_pigpio_version()
```

# get\_servo\_pulsewidth(user\_gpio)

Returns the servo pulsewidth being used on the GPIO.

#### **Parameters**

```
user_gpio:= 0-31.
```

Returns the servo pulsewidth.

#### **Example**

```
pi.set_servo_pulsewidth(4, 525)
print(pi.get_servo_pulsewidth(4))
525

pi.set_servo_pulsewidth(4, 2130)
print(pi.get_servo_pulsewidth(4))
2130
```

# gpio\_trigger(user\_gpio, pulse\_len, level)

Send a trigger pulse to a GPIO. The GPIO is set to level for pulse\_len microseconds and then reset to not level.

#### **Parameters**

```
user_gpio:= 0-31
pulse_len:= 1-100
```

#### Example

```
pi.qpio trigger(23, 10, 1)
```

## hardware\_PWM(gpio, PWMfreq, PWMduty)

Starts hardware PWM on a GPIO at the specified frequency and dutycycle. Frequencies above 30MHz are unlikely to work.

NOTE: Any waveform started by <u>wave\_send\_once</u>, <u>wave\_send\_repeat</u>, or <u>wave\_chain</u> will be cancelled.

This function is only valid if the pigpio main clock is PCM. The main clock defaults to PCM but may be overridden when the pigpio daemon is started (option -t).

#### **Parameters**

```
gpio:= see descripton
PWMfreq:= 0 (off) or 1-125000000 (125M).
PWMduty:= 0 (off) to 1000000 (1M)(fully on).
```

Returns 0 if OK, otherwise PI\_NOT\_PERMITTED, PI\_BAD\_GPIO, PI\_NOT\_HPWM\_GPIO, PI\_BAD\_HPWM\_DUTY, PI\_BAD\_HPWM\_FREQ.

The same PWM channel is available on multiple GPIO. The latest frequency and dutycycle setting will be used by all GPIO which share a PWM channel.

The GPIO must be one of the following:

```
12 PWM channel 0 All models but A and B
13 PWM channel 1 All models but A and B
18 PWM channel 0 All models
19 PWM channel 1 All models but A and B
40 PWM channel 0 Compute module only
41 PWM channel 1 Compute module only
45 PWM channel 1 Compute module only
52 PWM channel 0 Compute module only
53 PWM channel 1 Compute module only
```

The actual number of steps beween off and fully on is the integral part of 250 million divided by PWMfreq.

The actual frequency set is 250 million / steps.

There will only be a million steps for a PWMfreq of 250. Lower frequencies will have more steps and higher frequencies will have fewer steps. PWMduty is automatically scaled to take this into account.

#### Example

```
pi.hardware_PWM(18, 800, 250000) # 800Hz 25% dutycycle
pi.hardware PWM(18, 2000, 750000) # 2000Hz 75% dutycycle
```

# hardware\_clock(gpio, clkfreq)

Starts a hardware clock on a GPIO at the specified frequency. Frequencies above 30MHz are unlikely to work.

#### **Parameters**

```
gpio:= see description
clkfreq:= 0 (off) or 4689-250000000 (250M)
```

Returns 0 if OK, otherwise PI\_NOT\_PERMITTED, PI\_BAD\_GPIO, PI\_NOT\_HCLK\_GPIO, PI\_BAD\_HCLK\_FREQ, or PI\_BAD\_HCLK\_PASS.

The same clock is available on multiple GPIO. The latest frequency setting will be used by all GPIO which share a clock.

The GPIO must be one of the following:

```
d clock 0 All models
clock 1 All models but A and B (reserved for system use)
clock 2 All models but A and B
clock 0 All models but A and B
clock 1 All models but A and B
clock 1 All models but A and Rev.2 B (reserved for system use)

clock 0 Compute module only
clock 0 Compute module only
clock 1 Compute module only (reserved for system use)

clock 2 Compute module only
clock 1 Compute module only
clock 1 Compute module only
clock 1 Compute module only
```

Access to clock 1 is protected by a password as its use will likely crash the Pi. The password is given by or'ing 0x5A000000 with the GPIO number.

#### Example

```
pi.hardware_clock(4, 5000) # 5 KHz clock on GPIO 4
pi.hardware clock(4, 40000000) # 40 MHz clock on GPIO 4
```

# i2c\_block\_process\_call(handle, reg, data)

Writes data bytes to the specified register of the device associated with handle and reads a device specified number of bytes of data in return.

### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>i2c_open</u>).
  reg:= >=0, the device register.
  data:= the bytes to write.
```

The SMBus 2.0 documentation states that a minimum of 1 byte may be sent and a minimum of 1 byte may be received. The total number of bytes sent/received must be 32 or less.

```
SMBus 2.0 5.5.8 - Block write-block read.
```

```
S Addr Wr [A] reg [A] len(data) [A] data0 [A] ... datan [A] S Addr Rd [A] [Count] A [Data] ... A P
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

```
(b, d) = pi.i2c_block_process_call(h, 10, b'\x02\x05\x00')
(b, d) = pi.i2c_block_process_call(h, 10, b'abcdr')
(b, d) = pi.i2c_block_process_call(h, 10, "abracad")
(b, d) = pi.i2c_block_process_call(h, 10, [2, 5, 16])
```

## i2c\_close(handle)

Closes the I2C device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to \underline{i2c} open).
```

#### Example

```
pi.i2c_close(h)
```

## i2c\_open(i2c\_bus, i2c\_address, i2c\_flags)

Returns a handle (>=0) for the device at the I2C bus address.

#### **Parameters**

```
i2c_bus:= >=0.
i2c_address:= 0-0x7F.
i2c_flags:= 0, no flags are currently defined.
```

Normally you would only use the <u>i2c</u> \* functions if you are or will be connecting to the Pi over a network. If you will always run on the local Pi use the standard SMBus module instead.

Physically buses 0 and 1 are available on the Pi. Higher numbered buses will be available if a kernel supported bus multiplexor is being used.

For the SMBus commands the low level transactions are shown at the end of the function description. The following abbreviations are used:

```
S (1 bit): Start bit
P (1 bit): Stop bit
Rd/Wr (1 bit): Read/Write bit. Rd equals 1, Wr equals 0.
A, NA (1 bit): Accept and not accept bit.
Addr (7 bits): I2C 7 bit address.
reg (8 bits): Command byte, which often selects a register.
Data (8 bits): A data byte.
Count (8 bits): A byte defining the length of a block operation.
[..]: Data sent by the device.
```

### **Example**

```
h = pi.i2c\_open(1, 0x53) \# open device at address 0x53 on bus 1
```

# i2c\_process\_call(handle, reg, word\_val)

Writes 16 bits of data to the specified register of the device associated with handle and reads 16 bits of data in return.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to i2c_open).
    reg:= >=0, the device register.
word_val:= 0-65535, the value to write.

SMBus 2.0 5.5.6 - Process call.
S Addr Wr [A] reg [A] word_val_Low [A] word_val_High [A]
    S Addr Rd [A] [DataLow] A [DataHigh] NA P
```

#### Example

```
r = pi.i2c_process_call(h, 4, 0x1231)
r = pi.i2c_process_call(h, 6, 0)
```

## i2c\_read\_block\_data(handle, reg)

Reads a block of up to 32 bytes from the specified register of the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to i2c_open).
    reg:= >=0, the device register.

SMBus 2.0 5.5.7 - Block read.
S Addr Wr [A] reg [A]
    S Addr Rd [A] [Count] A [Data] A [Data] A ... A [Data] NA P
```

The amount of returned data is set by the device.

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

### Example

```
(b, d) = pi.i2c_read_block_data(h, 10)
if b >= 0:
    # process data
else:
    # process read failure
```

# i2c\_read\_byte(handle)

Reads a single byte from the device associated with handle.

### **Parameters**

```
handle:= >=0 (as returned by a prior call to i2c\_open).
```

### SMBus 2.0 5.5.3 - Receive byte.

```
S Addr Rd [A] [Data] NA P
```

```
b = pi.i2c read byte(2) # read a byte from device 2
```

# i2c\_read\_byte\_data(handle, reg)

Reads a single byte from the specified register of the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to <a href="i2c_open">i2c_open</a>).

reg:= >=0, the device register.

SMBus 2.0 5.5.5 - Read byte.

S Addr Wr [A] reg [A] S Addr Rd [A] [Data] NA P
```

#### Example

```
# read byte from reg 17 of device 2
b = pi.i2c_read_byte_data(2, 17)
# read byte from reg 1 of device 0
b = pi.i2c_read_byte_data(0, 1)
```

# i2c\_read\_device(handle, count)

Returns count bytes read from the raw device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>i2c_open</u>).
count:= >0, the number of bytes to read.

S Addr Rd [A] [Data] A [Data] A ... A [Data] NA P
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

#### Example

```
(count, data) = pi.i2c_read_device(h, 12)
```

# i2c\_read\_i2c\_block\_data(<u>handle</u>, <u>reg</u>, <u>count</u>)

Reads count bytes from the specified register of the device associated with handle . The count may be 1-32.

### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>i2c_open</u>).
    reg:= >=0, the device register.
count:= >0, the number of bytes to read.

S Addr Wr [A] reg [A]
    S Addr Rd [A] [Data] A [Data] A ... A [Data] NA P
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

#### Example

```
(b, d) = pi.i2c_read_i2c_block_data(h, 4, 32)
if b >= 0:
    # process data
else:
    # process read failure
```

## i2c\_read\_word\_data(handle, reg)

Reads a single 16 bit word from the specified register of the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>i2c_open</u>).
    reg:= >=0, the device register.

SMBus 2.0 5.5.5 - Read word.
S Addr Wr [A] reg [A] S Addr Rd [A] [DataLow] A [DataHigh] NA P
```

#### Example

```
# read word from reg 2 of device 3
w = pi.i2c_read_word_data(3, 2)
# read word from reg 7 of device 2
w = pi.i2c_read_word_data(2, 7)
```

## i2c\_write\_block\_data(<u>handle</u>, <u>reg</u>, <u>data</u>)

Writes up to 32 bytes to the specified register of the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to i2c open).
  reg:= >=0, the device register.
  data:= the bytes to write.

SMBus 2.0 5.5.7 - Block write.

S Addr Wr [A] reg [A] len(data) [A] data0 [A] data1 [A] ... [A] datan [A] P
```

#### Example

```
pi.i2c_write_block_data(4, 5, b'hello')
pi.i2c_write_block_data(4, 5, "data bytes")
pi.i2c_write_block_data(5, 0, b'\x00\x01\x22')
pi.i2c_write_block_data(6, 2, [0, 1, 0x22])
```

# i2c\_write\_byte(handle, byte\_val)

Sends a single byte to the device associated with handle.

### **Parameters**

```
handle:= >=0 (as returned by a prior call to \underline{i2c\_open}). byte_val:= 0-255, the value to write.
```

### SMBus 2.0 5.5.2 - Send byte.

```
S Addr Wr [A] byte_val [A] P
```

#### **Example**

## i2c\_write\_byte\_data(handle, reg, byte\_val)

Writes a single byte to the specified register of the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to i2c\_open).

reg:= >=0, the device register.

byte_val:= 0-255, the value to write.
```

### SMBus 2.0 5.5.4 - Write byte.

```
S Addr Wr [A] reg [A] byte val [A] P
```

#### **Example**

```
# send byte 0xC5 to reg 2 of device 1
pi.i2c_write_byte_data(1, 2, 0xC5)
# send byte 9 to reg 4 of device 2
pi.i2c_write_byte_data(2, 4, 9)
```

# i2c\_write\_device(handle, data)

Writes the data bytes to the raw device associated with handle.

### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>i2c_open</u>).
  data:= the bytes to write.

S Addr Wr [A] data0 [A] data1 [A] ... [A] datan [A] P
```

### Example

```
pi.i2c_write_device(h, b"\x12\x34\xA8")
pi.i2c_write_device(h, b"help")
pi.i2c_write_device(h, 'help')
pi.i2c_write_device(h, [23, 56, 231])
```

# i2c\_write\_i2c\_block\_data(handle, reg, data)

Writes data bytes to the specified register of the device associated with handle . 1-32 bytes may be written.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to i2c open).
   reg:= >=0, the device register.
   data:= the bytes to write.

S Addr Wr [A] reg [A] data0 [A] data1 [A] ... [A] datan [NA] P
```

#### Example

```
pi.i2c_write_i2c_block_data(4, 5, 'hello')
pi.i2c_write_i2c_block_data(4, 5, b'hello')
pi.i2c_write_i2c_block_data(5, 0, b'\x00\x01\x22')
pi.i2c_write_i2c_block_data(6, 2, [0, 1, 0x22])
```

## i2c\_write\_quick(handle, bit)

Sends a single bit to the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to i2c_open).
bit:= 0 or 1, the value to write.
```

#### SMBus 2.0 5.5.1 - Quick command.

```
S Addr bit [A] P
```

### Example

```
pi.i2c_write_quick(0, 1) # send 1 to device 0
pi.i2c_write_quick(3, 0) # send 0 to device 3
```

# i2c\_write\_word\_data(<u>handle</u>, <u>reg</u>, <u>word\_val</u>)

Writes a single 16 bit word to the specified register of the device associated with handle.

### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>i2c_open</u>).
    reg:= >=0, the device register.
word_val:= 0-65535, the value to write.
```

### SMBus 2.0 5.5.4 - Write word.

```
S Addr Wr [A] reg [A] word_val_Low [A] word_val_High [A] P
```

#### **Example**

```
# send word 0xA0C5 to reg 5 of device 4
pi.i2c_write_word_data(4, 5, 0xA0C5)
# send word 2 to reg 2 of device 5
pi.i2c_write_word_data(5, 2, 23)
```

# i2c\_zip(handle, data)

This function executes a sequence of I2C operations. The operations to be performed are specified by the contents of data which contains the concatenated command codes and associated data.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to i2c_open).
data:= the concatenated I2C commands, see below
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

#### Example

```
(count, data) = pi.i2c_zip(h, [4, 0x53, 7, 1, 0x32, 6, 6, 0])
```

The following command codes are supported:

| Name    | Cmd & Data | Meaning                           |
|---------|------------|-----------------------------------|
| End     | 0          | No more commands                  |
| Escape  | 1          | Next P is two bytes               |
| On      | 2          | Switch combined flag on           |
| Off     | 3          | Switch combined flag off          |
| Address | 4 P        | Set I2C address to P              |
| Flags   | 5 lsb msb  | Set I2C flags to lsb + (msb << 8) |
| Read    | 6 P        | Read P bytes of data              |
| Write   | 7 P        | Write P bytes of data             |

The address, read, and write commands take a parameter P. Normally P is one byte (0-255). If the command is preceded by the Escape command then P is two bytes (0-65535, least significant byte first).

The address defaults to that associated with the handle. The flags default to 0. The address and flags maintain their previous value until updated.

Any read I2C data is concatenated in the returned bytearray.

#### Example

# notify\_begin(handle, bits)

Starts notifications on a handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to notify_open)
```

```
bits:= a 32 bit mask indicating the GPIO to be notified.
```

The notification sends state changes for each GPIO whose corresponding bit in bits is set.

The following code starts notifications for GPIO 1, 4, 6, 7, and 10 (1234 = 0x04D2 = 0b0000010011010010).

#### Example

```
h = pi.notify_open()
if h >= 0:
   pi.notify_begin(h, 1234)
```

## notify\_close(handle)

Stops notifications on a handle and releases the handle for reuse.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to notify_open)
```

#### Example

```
h = pi.notify_open()
if h >= 0:
   pi.notify_begin(h, 1234)
   ...
   pi.notify_close(h)
```

## notify\_open()

Returns a notification handle (>=0).

A notification is a method for being notified of GPIO state changes via a pipe.

Pipes are only accessible from the local machine so this function serves no purpose if you are using Python from a remote machine. The in-built (socket) notifications provided by <u>callback</u> should be used instead.

Notifications for handle x will be available at the pipe named /dev/pigpiox (where x is the handle number).

E.g. if the function returns 15 then the notifications must be read from /dev/pigpio15.

Notifications have the following structure:

```
H seqno
H flags
I tick
I level
```

seqno: starts at 0 each time the handle is opened and then increments by one for each report.

flags: three flags are defined, PI\_NTFY\_FLAGS\_WDOG, PI\_NTFY\_FLAGS\_ALIVE, and PI\_NTFY\_FLAGS\_EVENT.

If bit 5 is set (PI\_NTFY\_FLAGS\_WDOG) then bits 0-4 of the flags indicate a GPIO which has had a watchdog timeout.

If bit 6 is set (PI\_NTFY\_FLAGS\_ALIVE) this indicates a keep alive signal on the pipe/socket and is sent once a minute in the absence of other notification activity.

If bit 7 is set (PI\_NTFY\_FLAGS\_EVENT) then bits 0-4 of the flags indicate an event which has been triggered.

tick: the number of microseconds since system boot. It wraps around after 1h12m.

level: indicates the level of each GPIO. If bit 1<<x is set then GPIO x is high.

#### Example

```
h = pi.notify_open()
if h >= 0:
   pi.notify begin(h, 1234)
```

# notify\_pause(handle)

Pauses notifications on a handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to notify_open)
```

Notifications for the handle are suspended until <u>notify\_begin</u> is called again.

#### Example

```
h = pi.notify_open()
if h >= 0:
    pi.notify_begin(h, 1234)
    ...
    pi.notify_pause(h)
    ...
    pi.notify_begin(h, 1234)
    ...
```

# read(gpio)

Returns the GPIO level.

### **Parameters**

```
gpio:= 0-53.
```

### Example

```
pi.set_mode(23, pigpio.INPUT)
pi.set_pull_up_down(23, pigpio.PUD_DOWN)
print(pi.read(23))
0
pi.set_pull_up_down(23, pigpio.PUD_UP)
print(pi.read(23))
```

# read\_bank\_1()

Returns the levels of the bank 1 GPIO (GPIO 0-31).

The returned 32 bit integer has a bit set if the corresponding GPIO is high. GPIO n has bit value (1<<n).

#### Example

```
print(bin(pi.read_bank_1()))
0b100101000000111100100001001111
```

## read\_bank\_2()

Returns the levels of the bank 2 GPIO (GPIO 32-53).

The returned 32 bit integer has a bit set if the corresponding GPIO is high. GPIO n has bit value (1<<(n-32)).

### Example

```
print(bin(pi.read_bank_2()))
0b11111100000000000000000
```

## run\_script(script\_id, params)

Runs a stored script.

#### **Parameters**

```
script_id:= id of stored script.
params:= up to 10 parameters required by the script.
```

#### **Example**

```
s = pi.run_script(sid, [par1, par2])
s = pi.run_script(sid)
s = pi.run_script(sid, [1, 2, 3, 4, 5, 6, 7, 8, 9, 10])
```

# script\_status(script\_id)

Returns the run status of a stored script as well as the current values of parameters 0 to 9.

#### **Parameters**

```
script_id:= id of stored script.
```

### The run status may be

```
PI_SCRIPT_INITING
PI_SCRIPT_HALTED
PI_SCRIPT_RUNNING
PI_SCRIPT_WAITING
PI_SCRIPT_FAILED
```

The return value is a tuple of run status and a list of the 10 parameters. On error the run status will be negative and the parameter list will be empty.

```
(s, pars) = pi.script status(sid)
```

# serial close(handle)

Closes the serial device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to serial_open).
```

### Example

```
pi.serial_close(h1)
```

# serial data available(handle)

Returns the number of bytes available to be read from the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to serial_open).
```

#### Example

```
rdy = pi.serial_data_available(h1)
if rdy > 0:
    (b, d) = pi.serial read(h1, rdy)
```

# serial\_open(tty, baud, ser\_flags)

Returns a handle for the serial tty device opened at baud bits per second. The device name must start with /dev/tty or /dev/serial.

### **Parameters**

```
tty:= the serial device to open.
baud:= baud rate in bits per second, see below.
ser_flags:= 0, no flags are currently defined.
```

Normally you would only use the <u>serial</u> functions if you are or will be connecting to the Pi over a network. If you will always run on the local Pi use the standard serial module instead.

The baud rate must be one of 50, 75, 110, 134, 150, 200, 300, 600, 1200, 1800, 2400, 4800, 9600, 19200, 38400, 57600, 115200, or 230400.

## Example

```
h1 = pi.serial_open("/dev/ttyAMA0", 300)
h2 = pi.serial_open("/dev/ttyUSB1", 19200, 0)
h3 = pi.serial_open("/dev/serial0", 9600)
```

# serial\_read(handle, count)

Reads up to count bytes from the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>serial_open</u>).
count:= >0, the number of bytes to read (defaults to 1000).
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

If no data is ready a bytes read of zero is returned. Example

```
(b, d) = pi.serial_read(h2, 100)
if b > 0:
    # process read data
```

# serial\_read\_byte(handle)

Returns a single byte from the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to serial_open).
```

If no data is ready a negative error code will be returned.

#### Example

```
b = pi.serial_read_byte(h1)
```

# serial\_write(handle, data)

Writes the data bytes to the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to serial_open).
data:= the bytes to write.
```

## **Example**

```
pi.serial_write(h1, b'\x02\x03\x04')
pi.serial_write(h2, b'help')
pi.serial_write(h2, "hello")
pi.serial write(h1, [2, 3, 4])
```

# serial\_write\_byte(<u>handle</u>, <u>byte\_val</u>)

Writes a single byte to the device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to \underline{\text{serial\_open}}). byte val:= 0-255, the value to write.
```

```
pi.serial_write_byte(h1, 23)
pi.serial write byte(h1, ord('Z'))
```

# set\_PWM\_dutycycle(<u>user\_gpio</u>, <u>dutycycle</u>)

Starts (non-zero dutycycle) or stops (0) PWM pulses on the GPIO.

#### **Parameters**

```
user_gpio:= 0-31.
dutycycle:= 0-range (range defaults to 255).
```

The <u>set PWM range</u> function can change the default range of 255.

#### Example

```
pi.set_PWM_dutycycle(4, 0) # PWM off
pi.set_PWM_dutycycle(4, 64) # PWM 1/4 on
pi.set_PWM_dutycycle(4, 128) # PWM 1/2 on
pi.set_PWM_dutycycle(4, 192) # PWM 3/4 on
pi.set_PWM_dutycycle(4, 255) # PWM full on
```

# set\_PWM\_frequency(<u>user\_gpio</u>, <u>frequency</u>)

Sets the frequency (in Hz) of the PWM to be used on the GPIO.

### **Parameters**

```
user_gpio:= 0-31.
frequency:= >=0 Hz
```

Returns the numerically closest frequency if OK, otherwise PI\_BAD\_USER\_GPIO or PI\_NOT\_PERMITTED.

If PWM is currently active on the GPIO it will be switched off and then back on at the new frequency.

Each GPIO can be independently set to one of 18 different PWM frequencies.

The selectable frequencies depend upon the sample rate which may be 1, 2, 4, 5, 8, or 10 microseconds (default 5). The sample rate is set when the pigpio daemon is started.

The frequencies for each sample rate are:

```
Hertz
     1: 40000 20000 10000 8000 5000 4000 2500 2000 1600
         1250 1000 800 500 400 250 200 100 50
     2: 20000 10000 5000 4000 2500 2000 1250 1000 800
         625 500 400 250 200 125 100 50 25
     4: 10000 5000 2500 2000 1250 1000 625 500 400
         313 250 200 125 100 63 50 25 13
sample
rate
(us) 5: 8000 4000 2000 1600 1000 800 500 400 320
         250 200 160 100 80 50 40 20 10
     8: 5000 2500 1250 1000 625 500 313 250 200
                  100 63 50
         156
             125
                                31
                                    25
                                        1.3
```

```
10: 4000 2000 1000 800 500 400 250 200 160 125 100 80 50 40 25 20 10 5
```

```
pi.set_PWM_frequency(4,0)
print(pi.get_PWM_frequency(4))
10
pi.set_PWM_frequency(4,100000)
print(pi.get_PWM_frequency(4))
8000
```

# set\_PWM\_range(user\_gpio, range\_)

Sets the range of PWM values to be used on the GPIO.

#### **Parameters**

```
user_gpio:= 0-31.
range := 25-40000.
```

### Example

```
pi.set_PWM_range(9, 100) # now 25 1/4, 50 1/2, 75 3/4 on
pi.set_PWM_range(9, 500) # now 125 1/4, 250 1/2, 375 3/4 on
pi.set PWM range(9, 3000) # now 750 1/4, 1500 1/2, 2250 3/4 on
```

# set\_bank\_1(bits)

Sets GPIO 0-31 if the corresponding bit in bits is set.

### **Parameters**

```
bits:= a 32 bit mask with 1 set if the corresponding GPIO is
    to be set.
```

A returned status of PI\_SOME\_PERMITTED indicates that the user is not allowed to write to one or more of the GPIO.

### Example

```
pi.set_bank_1(int("111110010000",2))
```

# set\_bank\_2(bits)

Sets GPIO 32-53 if the corresponding bit (0-21) in bits is set.

### **Parameters**

```
bits:= a 32 bit mask with 1 set if the corresponding GPIO is
    to be set.
```

A returned status of PI\_SOME\_PERMITTED indicates that the user is not allowed to write to one or more of the GPIO.

## **Example**

# set glitch filter(user gpio, steady)

Sets a glitch filter on a GPIO.

Level changes on the GPIO are not reported unless the level has been stable for at least <u>steady</u> microseconds. The level is then reported. Level changes of less than <u>steady</u> microseconds are ignored.

### **Parameters**

```
user_gpio:= 0-31
steady:= 0-300000
```

Returns 0 if OK, otherwise PI\_BAD\_USER\_GPIO, or PI\_BAD\_FILTER.

This filter affects the GPIO samples returned to callbacks set up with <u>callback</u> and <u>wait\_for\_edge</u>.

It does not affect levels read by read, read bank 1, or read bank 2.

Each (stable) edge will be timestamped steady microseconds after it was first detected.

### Example

```
pi.set glitch filter(23, 100)
```

# set\_mode(gpio, mode)

Sets the GPIO mode.

### **Parameters**

```
gpio:= 0-53.
mode:= INPUT, OUTPUT, ALT0, ALT1, ALT2, ALT3, ALT4, ALT5.
```

### Example

```
pi.set_mode( 4, pigpio.INPUT)  # GPIO  4 as input
pi.set_mode(17, pigpio.OUTPUT)  # GPIO 17 as output
pi.set_mode(24, pigpio.ALT2)  # GPIO 24 as ALT2
```

# set\_noise\_filter(<u>user\_gpio</u>, <u>steady</u>, <u>active</u>)

Sets a noise filter on a GPIO.

Level changes on the GPIO are ignored until a level which has been stable for <u>steady</u> microseconds is detected. Level changes on the GPIO are then reported for <u>active</u> microseconds after which the process repeats.

#### **Parameters**

```
user_gpio:= 0-31
  steady:= 0-300000
  active:= 0-1000000
```

Returns 0 if OK, otherwise PI BAD USER GPIO, or PI BAD FILTER.

This filter affects the GPIO samples returned to callbacks set up with <u>callback</u> and <u>wait\_for\_edge</u>.

It does not affect levels read by <u>read</u>, <u>read bank 1</u>, or <u>read bank 2</u>.

Level changes before and after the active period may be reported. Your software must be designed to cope with such reports.

#### Example

```
pi.set_noise_filter(23, 1000, 5000)
```

# set\_pad\_strength(pad, pad\_strength)

This function sets the pad drive strength in mA.

#### **Parameters**

```
pad:= 0-2, the pad to set.
pad_strength:= 1-16 mA.
```

Returns 0 if OK, otherwise PI BAD PAD, or PI BAD STRENGTH.

| Pad | GPIO  |
|-----|-------|
| 0   | 0-27  |
| 1   | 28-45 |
| 2   | 46-53 |

### Example

```
pi.set pad strength(2, 14) # Set pad 2 to 14 mA.
```

# set\_pull\_up\_down(gpio, pud)

Sets or clears the internal GPIO pull-up/down resistor.

## **Parameters**

```
gpio:= 0-53.
pud:= PUD_UP, PUD_DOWN, PUD_OFF.
```

## **Example**

```
pi.set_pull_up_down(17, pigpio.PUD_OFF)
pi.set_pull_up_down(23, pigpio.PUD_UP)
pi.set_pull_up_down(24, pigpio.PUD_DOWN)
```

# set\_servo\_pulsewidth(<u>user\_gpio</u>, <u>pulsewidth</u>)

Starts (500-2500) or stops (0) servo pulses on the GPIO.

### **Parameters**

```
user_gpio:= 0-31.
pulsewidth:= 0 (off),
```

```
500 (most anti-clockwise) - 2500 (most clockwise).
```

The selected pulsewidth will continue to be transmitted until changed by a subsequent call to set\_servo\_pulsewidth.

The pulsewidths supported by servos varies and should probably be determined by experiment. A value of 1500 should always be safe and represents the mid-point of rotation.

You can DAMAGE a servo if you command it to move beyond its limits.

## **Example**

```
pi.set_servo_pulsewidth(17, 0)  # off
pi.set_servo_pulsewidth(17, 1000) # safe anti-clockwise
pi.set_servo_pulsewidth(17, 1500) # centre
pi.set_servo_pulsewidth(17, 2000) # safe clockwise
```

# set\_watchdog(<u>user\_gpio</u>, <u>wdog\_timeout</u>)

Sets a watchdog timeout for a GPIO.

#### **Parameters**

```
user_gpio:= 0-31.
wdog timeout:= 0-60000.
```

The watchdog is nominally in milliseconds.

Only one watchdog may be registered per GPIO.

The watchdog may be cancelled by setting timeout to 0.

Once a watchdog has been started callbacks for the GPIO will be triggered every timeout interval after the last GPIO activity.

The callback will receive the special level TIMEOUT.

#### Example

```
pi.set_watchdog(23, 1000) # 1000 ms watchdog on GPIO 23
pi.set_watchdog(23, 0) # cancel watchdog on GPIO 23
```

# shell(shellscr, pstring)

This function uses the system call to execute a shell script with the given string as its parameter.

### **Parameters**

The exit status of the system call is returned if OK, otherwise PI\_BAD\_SHELL\_STATUS.

shellscr must exist in /opt/pigpio/cgi and must be executable.

The returned exit status is normally 256 times that set by the shell script exit function. If

the script can't be found 32512 will be returned.

The following table gives some example returned statuses:

| Script exit status | Returned system call status |
|--------------------|-----------------------------|
| 1                  | 256                         |
| 5                  | 1280                        |
| 10                 | 2560                        |
| 200                | 51200                       |
| script not found   | 32512                       |

#### Example

```
// pass two parameters, hello and world
status = pi.shell("scr1", "hello world");

// pass three parameters, hello, string with spaces, and world
status = pi.shell("scr1", "hello 'string with spaces' world");

// pass one parameter, hello string with spaces world
status = pi.shell("scr1", "\"hello string with spaces world\"");
```

# spi\_close(handle)

Closes the SPI device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to spi_open).
```

### **Example**

```
pi.spi_close(h)
```

# spi\_open(spi\_channel, baud, spi\_flags)

Returns a handle for the SPI device on channel. Data will be transferred at baud bits per second. The flags may be used to modify the default behaviour of 4-wire operation, mode 0, active low chip select.

An auxiliary SPI device is available on all models but the A and B and may be selected by setting the A bit in the flags. The auxiliary device has 3 chip selects and a selectable word size in bits.

### **Parameters**

Normally you would only use the <u>spi</u> functions if you are or will be connecting to the Pi over a network. If you will always run on the local Pi use the standard SPI module instead.

spi flags consists of the least significant 22 bits.

```
21 20 19 18 17 16 15 14 13 12 11 10 9 8 7 6 5 4 3 2 1 0 b b b b b R T n n n n W A u2 u1 u0 p2 p1 p0 m m
```

mm defines the SPI mode.

WARNING: modes 1 and 3 do not appear to work on the auxiliary device.

```
Mode POL PHA
0 0 0
1 0 1
2 1 0
3 1 1
```

px is 0 if CEx is active low (default) and 1 for active high.

ux is 0 if the CEx GPIO is reserved for SPI (default) and 1 otherwise.

A is 0 for the standard SPI device, 1 for the auxiliary SPI.

W is 0 if the device is not 3-wire, 1 if the device is 3-wire. Standard SPI device only.

nnnn defines the number of bytes (0-15) to write before switching the MOSI line to MISO to read data. This field is ignored if W is not set. Standard SPI device only.

T is 1 if the least significant bit is transmitted on MOSI first, the default (0) shifts the most significant bit out first. Auxiliary SPI device only.

R is 1 if the least significant bit is received on MISO first, the default (0) receives the most significant bit first. Auxiliary SPI device only.

bbbbbb defines the word size in bits (0-32). The default (0) sets 8 bits per word. Auxiliary SPI device only.

The <u>spi\_read</u>, <u>spi\_write</u>, and <u>spi\_xfer</u> functions transfer data packed into 1, 2, or 4 bytes according to the word size in bits.

For bits 1-8 there will be one byte per character.

For bits 9-16 there will be two bytes per character.

For bits 17-32 there will be four bytes per character.

Multi-byte transfers are made in least significant byte first order.

E.g. to transfer 32 11-bit words data should contain 64 bytes.

E.g. to transfer the 14 bit value 0x1ABC send the bytes 0xBC followed by 0x1A.

The other bits in flags should be set to zero.

### Example

```
# open SPI device on channel 1 in mode 3 at 50000 bits per second
h = pi.spi_open(1, 50000, 3)
```

# spi\_read(handle, count)

Reads count bytes from the SPI device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to spi_open).
count:= >0, the number of bytes to read.
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

#### Example

```
(b, d) = pi.spi_read(h, 60) # read 60 bytes from device h
if b == 60:
    # process read data
else:
    # error path
```

# spi\_write(handle, data)

Writes the data bytes to the SPI device associated with handle.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>spi_open</u>).
  data:= the bytes to write.
```

### **Example**

```
pi.spi_write(0, b'\x02\xc0\x80') # write 3 bytes to device 0
pi.spi_write(0, b'defgh') # write 5 bytes to device 0
pi.spi_write(0, "def") # write 3 bytes to device 0
pi.spi_write(1, [2, 192, 128]) # write 3 bytes to device 1
```

# spi\_xfer(handle, data)

Writes the data bytes to the SPI device associated with handle, returning the data bytes read from the device.

#### **Parameters**

```
handle:= >=0 (as returned by a prior call to <u>spi_open</u>).
  data:= the bytes to write.
```

The returned value is a tuple of the number of bytes read and a bytearray containing the bytes. If there was an error the number of bytes read will be less than zero (and will contain the error code).

## **Example**

```
(count, rx_data) = pi.spi_xfer(h, b'\x01\x80\x00')
(count, rx_data) = pi.spi_xfer(h, [1, 128, 0])
(count, rx_data) = pi.spi_xfer(h, b"hello")
(count, rx_data) = pi.spi_xfer(h, "hello")
```

# stop()

Release pigpio resources.

```
pi.stop()
```

# stop\_script(script\_id)

Stops a running script.

#### **Parameters**

```
script_id:= id of stored script.
```

#### Example

```
status = pi.stop_script(sid)
```

# store\_script(script)

Store a script for later execution.

See <a href="http://abyz.me.uk/rpi/pigpio/pigs.html#Scripts">http://abyz.me.uk/rpi/pigpio/pigs.html#Scripts</a> for details.

### **Parameters**

```
script:= the script text as a series of bytes.
```

Returns a >=0 script id if OK.

## Example

```
sid = pi.store_script(
   b'tag 0 w 22 1 mils 100 w 22 0 mils 100 dcr p0 jp 0')
```

# update\_script(script\_id, params)

Sets the parameters of a script. The script may or may not be running. The first parameters of the script are overwritten with the new values.

### **Parameters**

```
script_id:= id of stored script.
params:= up to 10 parameters required by the script.
```

## **Example**

```
s = pi.update_script(sid, [par1, par2])
s = pi.update_script(sid, [1, 2, 3, 4, 5, 6, 7, 8, 9, 10])
```

# wait\_for\_edge(user\_gpio, edge, wait\_timeout)

Wait for an edge event on a GPIO.

## **Parameters**

```
wait_timeout:= >=0.0 (default 60.0).
```

The function returns when the edge is detected or after the number of seconds specified by timeout has expired.

Do not use this function for precise timing purposes, the edge is only checked 20 times a second. Whenever you need to know the accurate time of GPIO events use a <u>callback</u> function.

The function returns True if the edge is detected, otherwise False.

### **Example**

```
if pi.wait_for_edge(23):
    print("Rising edge detected")
else:
    print("wait for edge timed out")

if pi.wait_for_edge(23, pigpio.FALLING_EDGE, 5.0):
    print("Falling edge detected")
else:
    print("wait for falling edge timed out")
```

# wait\_for\_event(event, wait\_timeout)

Wait for an event.

#### **Parameters**

```
event:= 0-31.
wait_timeout:= >=0.0 (default 60.0).
```

The function returns when the event is signalled or after the number of seconds specified by timeout has expired.

The function returns True if the event is detected, otherwise False.

## **Example**

```
if pi.wait_for_event(23):
    print("event detected")
else:
    print("wait for event timed out")
```

# wave\_add\_generic(pulses)

Adds a list of pulses to the current waveform.

#### **Parameters**

```
pulses:= list of pulses to add to the waveform.
```

Returns the new total number of pulses in the current waveform.

The pulses are interleaved in time order within the existing waveform (if any).

Merging allows the waveform to be built in parts, that is the settings for GPIO#1 can be added, and then GPIO#2 etc.

If the added waveform is intended to start after or within the existing waveform then the first pulse should consist solely of a delay.

```
G1 = 4
G2 = 24
pi.set_mode(G1, pigpio.OUTPUT)
pi.set mode(G2, pigpio.OUTPUT)
flash 500=[] # flash every 500 ms
flash 100=[] # flash every 100 ms
                               ON OFF DELAY
flash_500.append(pigpio.pulse(1<<G1, 1<<G2, 500000))
flash 500.append(pigpio.pulse(1<<G2, 1<<G1, 500000))
flash 100.append(pigpio.pulse(1<<G1, 1<<G2, 100000))
flash 100.append(pigpio.pulse(1<<G2, 1<<G1, 100000))
pi.wave_clear() # clear any existing waveforms
pi.wave_add_generic(flash_500) # 500 ms flashes
f500 = pi.wave_create() # create and save id
pi.wave add generic(flash 100) # 100 ms flashes
f100 = pi.wave create() # create and save id
pi.wave send repeat(f500)
time.sleep(4)
pi.wave send repeat(f100)
time.sleep(4)
pi.wave send repeat(f500)
time.sleep(4)
pi.wave_tx_stop() # stop waveform
pi.wave clear() # clear all waveforms
```

# wave\_add\_new()

Starts a new empty waveform.

You would not normally need to call this function as it is automatically called after a waveform is created with the <u>wave\_create</u> function.

#### Example

```
pi.wave_add_new()
```

# wave\_add\_serial(user\_gpio, baud, data, offset, bb\_bits, bb\_stop)

Adds a waveform representing serial data to the existing waveform (if any). The serial data starts offset microseconds from the start of the waveform.

## **Parameters**

```
bb_bits:= number of data bits, default 8.
bb stop:= number of stop half bits, default 2.
```

Returns the new total number of pulses in the current waveform.

The serial data is formatted as one start bit, bb bits data bits, and bb stop/2 stop bits.

It is legal to add serial data streams with different baud rates to the same waveform.

The bytes required for each character depend upon **bb\_bits**.

```
For <u>bb_bits</u> 1-8 there will be one byte per character.
For <u>bb_bits</u> 9-16 there will be two bytes per character.
For <u>bb_bits</u> 17-32 there will be four bytes per character.
```

#### Example

```
pi.wave_add_serial(4, 300, 'Hello world')
pi.wave_add_serial(4, 300, b"Hello world")
pi.wave_add_serial(4, 300, b'\x23\x01\x00\x45')
pi.wave_add_serial(17, 38400, [23, 128, 234], 5000)
```

# wave chain(data)

This function transmits a chain of waveforms.

NOTE: Any hardware PWM started by <u>hardware PWM</u> will be cancelled.

The waves to be transmitted are specified by the contents of data which contains an ordered list of <u>wave\_id</u>s and optional command codes and related data.

```
Returns 0 if OK, otherwise PI_CHAIN_NESTING, PI_CHAIN_LOOP_CNT, PI_BAD_CHAIN_LOOP, PI_BAD_CHAIN_CMD, PI_CHAIN_COUNTER, PI_BAD_CHAIN_DELAY, PI_CHAIN_TOO_BIG, or PI_BAD_WAVE_ID.
```

Each wave is transmitted in the order specified. A wave may occur multiple times per chain.

A blocks of waves may be transmitted multiple times by using the loop commands. The block is bracketed by loop start and end commands. Loops may be nested.

Delays between waves may be added with the delay command.

The following command codes are supported:

| Name         | Cmd & Data | Meaning                        |
|--------------|------------|--------------------------------|
| Loop Start   | 255 0      | Identify start of a wave block |
| Loop Repeat  | 255 1 x y  | loop x + y*256 times           |
| Delay        | 255 2 x y  | delay x + y*256 microseconds   |
| Loop Forever | 255 3      | loop forever                   |

If present Loop Forever must be the last entry in the chain.

The code is currently dimensioned to support a chain with roughly 600 entries and 20 loop counters.

```
#!/usr/bin/env python
import time
import pigpio
WAVES=5
GPIO=4
wid=[0]*WAVES
pi = pigpio.pi() # Connect to local Pi.
pi.set mode(GPIO, pigpio.OUTPUT);
for i in range (WAVES):
   pi.wave_add_generic([
       pigpio.pulse(1<<GPIO, 0, 20),
       pigpio.pulse(0, 1<<GPIO, (i+1)*200)]);
   wid[i] = pi.wave create();
pi.wave chain([
   \operatorname{wid}[4], \operatorname{wid}[3], \operatorname{wid}[2],
                                         # transmit waves 4+3+2
                                          # loop start
    255, 0,
       wid[0], wid[0], wid[0],  # transmit waves 0+0+0
255, 0,  # loop start
       255, 0, # loop start
wid[0], wid[1], # transmit waves 0+1
255, 2, 0x88, 0x13, # delay 5000us
255, 1, 30, 0, # loop end (repeat 30 times)
# loop start
# loop start
       255, 0,
                                           # loop start
           wid[2], wid[3], wid[0], # transmit waves 2+3+0
           wid[3], wid[1], wid[2], # transmit waves 3+1+2
       255, 1, 10, 0,
                                          # loop end (repeat 10 times)
# loop end (repeat 5 times)
   255, 1, 5, 0,
   wid[4], wid[4], wid[4], # transmit waves 4+4+4 255, 2, 0x20, 0x4E, # delay 20000us wid[0], wid[0], # transmit waves 0+0+0
while pi.wave tx busy():
   time.sleep(0.1);
for i in range (WAVES):
   pi.wave delete(wid[i])
pi.stop()
```

# wave\_clear()

Clears all waveforms and any data added by calls to the wave add \* functions.

### Example

```
pi.wave_clear()
```

## wave\_create()

Creates a waveform from the data provided by the prior calls to the <u>wave\_add\_\*</u> functions.

```
Returns a wave id (>=0) if OK, otherwise PI_EMPTY_WAVEFORM, PI TOO MANY CBS, PI TOO MANY OOL, or PI NO WAVEFORM ID.
```

The data provided by the <u>wave\_add\_\*</u> functions is consumed by this function.

As many waveforms may be created as there is space available. The wave id is passed to <u>wave\_send\_\*</u> to specify the waveform to transmit.

Normal usage would be

Step 1. wave clear to clear all waveforms and added data.

Step 2. wave add \* calls to supply the waveform data.

Step 3. wave\_create to create the waveform and get a unique id

Repeat steps 2 and 3 as needed.

Step 4. wave send \* with the id of the waveform to transmit.

A waveform comprises one or more pulses.

A pulse specifies

- 1) the GPIO to be switched on at the start of the pulse.
- 2) the GPIO to be switched off at the start of the pulse.
- 3) the delay in microseconds before the next pulse.

Any or all the fields can be zero. It doesn't make any sense to set all the fields to zero (the pulse will be ignored).

When a waveform is started each pulse is executed in order with the specified delay between the pulse and the next.

### Example

```
wid = pi.wave create()
```

# wave\_delete(wave\_id)

This function deletes the waveform with id wave id.

#### **Parameters**

```
wave_id:= >=0 (as returned by a prior call to wave_create).
```

Wave ids are allocated in order, 0, 1, 2, etc.

The wave is flagged for deletion. The resources used by the wave will only be reused when either of the following apply.

- all waves with higher numbered wave ids have been deleted or have been flagged for deletion.
- a new wave is created which uses exactly the same resources as the current wave (see the C source for gpioWaveCreate for details).

## Example

```
pi.wave_delete(6) # delete waveform with id 6
pi.wave delete(0) # delete waveform with id 0
```

# wave\_get\_cbs()

Returns the length in DMA control blocks of the current waveform.

```
cbs = pi.wave get cbs()
```

# wave\_get\_max\_cbs()

Returns the maximum possible size of a waveform in DMA control blocks.

## Example

```
cbs = pi.wave_get_max_cbs()
```

# wave\_get\_max\_micros()

Returns the maximum possible size of a waveform in microseconds.

### Example

```
micros = pi.wave get max micros()
```

# wave\_get\_max\_pulses()

Returns the maximum possible size of a waveform in pulses.

## Example

```
pulses = pi.wave_get_max_pulses()
```

# wave get micros()

Returns the length in microseconds of the current waveform.

## Example

```
micros = pi.wave_get_micros()
```

# wave\_get\_pulses()

Returns the length in pulses of the current waveform.

## **Example**

```
pulses = pi.wave_get_pulses()
```

# wave\_send\_once(wave\_id)

Transmits the waveform with id wave id. The waveform is sent once.

NOTE: Any hardware PWM started by <a href="hardware\_PWM">hardware\_PWM</a> will be cancelled.

### **Parameters**

```
wave_id:= >=0 (as returned by a prior call to wave_create).
```

Returns the number of DMA control blocks used in the waveform.

### Example

## wave send repeat(wave id)

Transmits the waveform with id wave\_id. The waveform repeats until wave\_tx\_stop is called or another call to <a href="wave\_send">wave\_send</a>\* is made.

NOTE: Any hardware PWM started by <a href="hardware\_PWM">hardware\_PWM</a> will be cancelled.

#### **Parameters**

```
wave_id:= >=0 (as returned by a prior call to <a href="wave_create">wave_create</a>).
```

Returns the number of DMA control blocks used in the waveform.

#### Example

```
cbs = pi.wave_send_repeat(wid)
```

## wave send using mode(wave\_id, mode)

Transmits the waveform with id wave id using mode mode.

#### **Parameters**

WAVE MODE ONE SHOT: same as wave send once.

WAVE MODE REPEAT same as wave send repeat.

WAVE\_MODE\_ONE\_SHOT\_SYNC same as <a href="wave\_send\_once">wave\_send\_once</a> but tries to sync with the previous waveform.

WAVE\_MODE\_REPEAT\_SYNC same as <u>wave\_send\_repeat</u> but tries to sync with the previous waveform.

WARNING: bad things may happen if you delete the previous waveform before it has been synced to the new waveform.

NOTE: Any hardware PWM started by <u>hardware PWM</u> will be cancelled.

### **Parameters**

```
wave id:= >=0 (as returned by a prior call to wave create).
```

Returns the number of DMA control blocks used in the waveform.

## **Example**

```
cbs = pi.wave send using mode(wid, WAVE MODE REPEAT SYNC)
```

## wave\_tx\_at()

Returns the id of the waveform currently being transmitted.

Returns the waveform id or one of the following special values:

WAVE\_NOT\_FOUND (9998) - transmitted wave not found. NO\_TX\_WAVE (9999) - no wave being transmitted.

### Example

```
wid = pi.wave_tx_at()
```

# wave\_tx\_busy()

Returns 1 if a waveform is currently being transmitted, otherwise 0.

### Example

```
pi.wave_send_once(0) # send first waveform
while pi.wave_tx_busy(): # wait for waveform to be sent
    time.sleep(0.1)
pi.wave_send_once(1) # send next waveform
```

# wave\_tx\_repeat()

This function is deprecated and has been removed.

Use wave create/wave send \* instead.

# wave\_tx\_start()

This function is deprecated and has been removed.

Use wave create/wave send \* instead.

# wave\_tx\_stop()

Stops the transmission of the current waveform.

This function is intended to stop a waveform started with wave send repeat.

#### Example

```
pi.wave_send_repeat(3)
time.sleep(5)
pi.wave tx stop()
```

# write(gpio, level)

Sets the GPIO level.

### **Parameters**

```
GPIO:= 0-53.
level:= 0, 1.
```

If PWM or servo pulses are active on the GPIO they are switched off.

```
pi.set_mode(17, pigpio.OUTPUT)
pi.write(17,0)
print(pi.read(17))
0

pi.write(17,1)
print(pi.read(17))
```

# class pulse

# pigpio.pulse(gpio\_on, gpio\_off, delay)

Initialises a pulse.

#### **Parameters**

```
gpio_on:= the GPIO to switch on at the start of the pulse.
gpio_off:= the GPIO to switch off at the start of the pulse.
delay:= the delay in microseconds before the next pulse.
```

# **FUNCTIONS**

# pigpio.error\_text(errnum)

Returns a text description of a pigpio error.

## **Parameters**

```
errnum:= <0, the error number
```

### Example

```
print(pigpio.error_text(-5))
level not 0-1
```

# pigpio.tickDiff(t1, t2)

Returns the microsecond difference between two ticks.

#### **Parameters**

```
t1:= the earlier tick
t2:= the later tick
```

## Example

```
print(pigpio.tickDiff(4294967272, 12))
36
```

# pigpio.u2i(uint32)

Converts a 32 bit unsigned number to signed.

#### **Parameters**

```
uint32:= an unsigned 32 bit number
```

### Example

```
print(u2i(4294967272))
-24
print(u2i(37))
37
```

# **PARAMETERS**

## active: 0-1000000

The number of microseconds level changes are reported for once a noise filter has been triggered (by <u>steady</u> microseconds of a stable level).

# arg1:

An unsigned argument passed to a user customised function. Its meaning is defined by the customiser.

# arg2:

An unsigned argument passed to a user customised function. Its meaning is defined by the customiser.

# argx:

An array of bytes passed to a user customised function. Its meaning and content is defined by the customiser.

## baud:

The speed of serial communication (I2C, SPI, serial link, waves) in bits per second.

# bb\_bits: 1-32

The number of data bits to be used when adding serial data to a waveform.

# **bb\_stop: 2-8**

The number of (half) stop bits to be used when adding serial data to a waveform.

## bit: 0-1

A value of 0 or 1.

## bits: 32 bit number

A mask used to select GPIO to be operated on. If bit n is set then GPIO n is selected. A convenient way of setting bit n is to bit or in the value (1<<n).

To select GPIO 1, 7, 23

```
bits = (1<<1) | (1<<7) | (1<<23)
```

# bsc\_control:

```
22 21 20 19 18 17 16 15 14 13 12 11 10 9 8 7 6 5 4 3 2 1 0 a a a a a a a - - IT HC TF IR RE TE BK EC ES PL PH I2 SP EN
```

aaaaaaa defines the I2C slave address (only relevant in I2C mode)

Bits 0-13 are copied unchanged to the BSC CR register. See pages 163-165 of the Broadcom peripherals document.

byte\_val: 0-255

A whole number.

clkfreq: 4689-250M

The hardware clock frequency.

## connected:

True if a connection was established, False otherwise.

## count:

The number of bytes of data to be transferred.

## CS:

The GPIO used for the slave select signal when bit banging SPI.

## data:

Data to be transmitted, a series of bytes.

# delay: >=1

The length of a pulse in microseconds.

# dutycycle: 0-range\_

A number between 0 and range .

The dutycycle sets the proportion of time on versus time off during each PWM cycle.

| Dutycycle     | On time |
|---------------|---------|
| 0             | Off     |
| range_ * 0.25 | 25% On  |
| range_ * 0.50 | 50% On  |

| range_ * 0 | .75 75% On |
|------------|------------|
| range_     | Fully On   |

# edge: 0-2

EITHER\_EDGE = 2 FALLING\_EDGE = 1 RISING EDGE = 0

## errnum: <0

```
PI_BAD_USER_GPIO = -2
PI BAD GPIO = -3
PI BAD MODE = -4
PI_BAD_LEVEL = -5
PI_BAD_PUD = -6
PI BAD PULSEWIDTH = -7
PI BAD DUTYCYCLE = -8
PI BAD WDOG TIMEOUT = -15
PI BAD DUTYRANGE = -21
PI_NO_HANDLE = -24
PI_BAD_HANDLE = -25
PI BAD WAVE BAUD = -35
PI TOO MANY PULSES = -36
PI TOO MANY CHARS = -37
PI_NOT_SERIAL_GPIO = -38
PI_NOT_PERMITTED = -41
PI_SOME_PERMITTED = -42
PI_BAD_WVSC_COMMND = -43
PI BAD WVSM COMMND = -44
PI BAD WVSP COMMND = -45
PI_BAD_PULSELEN = -46
PI_BAD_SCRIPT = -47
PI_BAD_SCRIPT_ID = -48
PI_BAD_SER_OFFSET = -49
PI GPIO IN USE = -50
PI BAD SERIAL COUNT = -51
PI_BAD_PARAM_NUM = -52
PI_DUP_TAG = -53
PI_TOO_MANY_TAGS = -54
PI BAD SCRIPT_CMD = -55
PI BAD VAR NUM = -56
PI_NO_SCRIPT_ROOM = -57
PI_NO_MEMORY = -58
PI_SOCK_READ_FAILED = -59
PI_SOCK_WRIT_FAILED = -60
PI_TOO_MANY_PARAM = -61
PI SCRIPT NOT READY = -62
PI_BAD_TAG = -63
PI_BAD_MICS_DELAY = -64
PI_BAD_MILS_DELAY = -65
PI_BAD_WAVE_ID = -66
PI TOO MANY CBS = -67
PI TOO MANY OOL = -68
PI EMPTY WAVEFORM = -69
PI_NO_WAVEFORM_ID = -70
PI_I2C_OPEN_FAILED = -71
PI_SER_OPEN_FAILED = -72
PI_SPI_OPEN_FAILED = -73
PI BAD I2C BUS = -74
PI_BAD_I2C_ADDR = -75
PI_BAD_SPI_CHANNEL = -76
PI_BAD_FLAGS = -77
PI BAD SPI SPEED = -78
PI BAD SER DEVICE = -79
PI BAD SER SPEED = -80
PI_BAD_PARAM = -81
PI_I2C_WRITE_FAILED = -82
PI_I2C_READ_FAILED = -83
PI_BAD_SPI_COUNT = -84
PI SER WRITE FAILED = -85
```

```
PI SER READ FAILED = -86
PI SER READ NO DATA = -87
PI UNKNOWN COMMAND = -88
PI SPI XFER FAILED = -89
PI NO AUX SPI = -91
PI_NOT_PWM_GPIO = -92
PI_NOT_SERVO_GPIO = -93
PI_NOT_HCLK_GPIO = -94
PI NOT HPWM GPIO = -95
PI BAD HPWM FREQ = -96
PI_BAD_HPWM_DUTY = -97
PI_BAD_HCLK_FREQ = -98
PI BAD HCLK PASS = -99
PI HPWM ILLEGAL = -100
PI BAD DATABITS = -101
PI BAD STOPBITS = -102
PI_MSG_TOOBIG = -103
PI_BAD_MALLOC_MODE = -104
PI BAD SMBUS CMD = -107
PINOTI2C GPIO = -108
PI BAD I2C WLEN = -109
PI BAD I2C RLEN = -110
PI_BAD_I2C_CMD = -111
PI_BAD_I2C_BAUD = -112
PI CHAIN LOOP CNT = -113
PI BAD CHAIN LOOP = -114
PI CHAIN COUNTER = -115
PI_BAD_CHAIN_CMD = -116
PI_BAD_CHAIN_DELAY = -117
PI_CHAIN_NESTING = -118
PI_CHAIN_TOO_BIG = -119
PI DEPRECATED = -120
PI BAD SER INVERT = -121
PI_BAD_FOREVER = -124
PI_BAD_FILTER = -125
PI_BAD_PAD = -126
PI_BAD_STRENGTH = -127
PI FIL OPEN FAILED = -128
PI BAD FILE MODE = -129
PI BAD FILE FLAG = -130
PI_BAD_FILE_READ = -131
PI BAD FILE WRITE = -132
PI \overline{FILE} NOT \overline{ROPEN} = -133
PI FILE NOT WOPEN = -134
PI BAD FILE SEEK = -135
PI_NO_FILE_MATCH = -136
PI_NO_FILE_ACCESS = -137
PI FILE IS A DIR = -138
PI_BAD_SHELL_STATUS = -139
PI BAD SCRIPT NAME = -140
PI BAD SPI BAUD = -141
PI_NOT_SPI_GPIO = -142
PI BAD EVENT ID = -143
PI CMD INTERRUPTED = -144
```

# event: 0-31

An event is a signal used to inform one or more consumers to start an action.

# file\_mode:

The mode may have the following values

```
FILE_READ 1
FILE_WRITE 2
FILE RW 3
```

The following values can be or'd into the file open mode

```
FILE_APPEND 4
FILE_CREATE 8
FILE TRUNC 16
```

# file\_name:

A full file path. To be accessible the path must match an entry in /opt/pigpio/access.

# fpattern:

A file path which may contain wildcards. To be accessible the path must match an entry in /opt/pigpio/access.

# frequency: 0-40000

Defines the frequency to be used for PWM on a GPIO. The closest permitted frequency will be used.

## func:

A user supplied callback function.

# gpio: 0-53

A Broadcom numbered GPIO. All the user GPIO are in the range 0-31.

There are 54 General Purpose Input Outputs (GPIO) named GPIO0 through GPIO53.

They are split into two banks. Bank 1 consists of GPIO0 through GPIO31. Bank 2 consists of GPIO32 through GPIO53.

All the GPIO which are safe for the user to read and write are in bank 1. Not all GPIO in bank 1 are safe though. Type 1 boards have 17 safe GPIO. Type 2 boards have 21. Type 3 boards have 26.

See get hardware revision.

The user GPIO are marked with an X in the following table

# gpio\_off:

A mask used to select GPIO to be operated on. See bits.

This mask selects the GPIO to be switched off at the start of a pulse.

# gpio\_on:

A mask used to select GPIO to be operated on. See bits.

This mask selects the GPIO to be switched on at the start of a pulse.

## handle: >=0

A number referencing an object opened by one of the following

```
file_open
i2c_open
notify_open
serial_open
spi_open
```

## host:

The name or IP address of the Pi running the pigpio daemon.

# i2c\_\*:

One of the i2c functions.

# i2c\_address: 0-0x7F

The address of a device on the I2C bus.

```
i2c_bus: >=0
```

An I2C bus number.

# i2c\_flags: 0

No I2C flags are currently defined.

## invert: 0-1

A flag used to set normal or inverted bit bang serial data level logic.

# level: 0-1 (2)

```
CLEAR = 0 

\mbox{HIGH} = 1 

\mbox{LOW} = 0 

\mbox{OFF} = 0 

\mbox{ON} = 1 

\mbox{SET} = 1 

\mbox{TIMEOUT} = 2 # only returned for a watchdog timeout
```

## MISO:

The GPIO used for the MISO signal when bit banging SPI.

## mode:

1. The operational mode of a GPIO, normally INPUT or OUTPUT.

```
ALT0 = 4

ALT1 = 5

ALT2 = 6

ALT3 = 7

ALT4 = 3

ALT5 = 2

INPUT = 0

OUTPUT = 1
```

2. The mode of waveform transmission.

```
WAVE_MODE_ONE_SHOT = 0
WAVE_MODE_REPEAT = 1
WAVE_MODE_ONE_SHOT_SYNC = 2
WAVE_MODE_REPEAT_SYNC = 3
```

## MOSI:

The GPIO used for the MOSI signal when bit banging SPI.

# offset: >=0

The offset wave data starts from the beginning of the waveform being currently defined.

# pad: 0-2

A set of GPIO which share common drivers.

| Pad | GPIO  |
|-----|-------|
| 0   | 0-27  |
| 1   | 28-45 |
| 2   | 46-53 |

# pad\_strength: 1-16

The mA which may be drawn from each GPIO whilst still guaranteeing the high and low levels.

# params: 32 bit number

When scripts are started they can receive up to 10 parameters to define their operation.

# port:

The port used by the pigpio daemon, defaults to 8888.

# pstring:

The string to be passed to a shell script to be executed.

# pud: 0-2

```
PUD_DOWN = 1
PUD_OFF = 0
PUD_UP = 2
```

pulse\_len: 1-100

The length of the trigger pulse in microseconds.

# pulses:

A list of class pulse objects defining the characteristics of a waveform.

# pulsewidth:

The servo pulsewidth in microseconds. 0 switches pulses off.

PWMduty: 0-1000000 (1M)

The hardware PWM dutycycle.

PWMfreq: 1-125000000 (125M)

The hardware PWM frequency.

range\_: 25-40000

Defines the limits for the dutycycle parameter.

range\_ defaults to 255.

reg: 0-255

An I2C device register. The usable registers depend on the actual device.

retMax: >=0

The maximum number of bytes a user customised function should return, default 8192.

SCL:

The user GPIO to use for the clock when bit banging I2C.

SCLK::

The GPIO used for the SCLK signal when bit banging SPI.

script:

The text of a script to store on the pigpio daemon.

script\_id: >=0

A number referencing a script created by store script.

SDA:

The user GPIO to use for data when bit banging I2C.

# seek\_from: 0-2

Direction to seek for file seek.

```
FROM_START=0
FROM_CURRENT=1
FROM_END=2
```

# seek\_offset:

The number of bytes to move forward (positive) or backwards (negative) from the seek position (start, current, or end of file).

```
ser_flags: 32 bit
```

No serial flags are currently defined.

# serial\_\*:

One of the serial functions.

## shellscr:

The name of a shell script. The script must exist in /opt/pigpio/cgi and must be executable.

# show\_errors:

Controls the display of pigpio daemon connection failures. The default of True prints the probable failure reasons to standard output.

# spi\_\*:

One of the spi\_ functions.

# spi channel: 0-2

A SPI channel.

spi\_flags: 32 bit

See spi\_open.

# steady: 0-300000

The number of microseconds level changes must be stable for before reporting the level changed (<u>set\_glitch\_filter</u>) or triggering the active part of a noise filter (<u>set\_noise\_filter</u>).

## t1:

A tick (earlier).

## t2:

A tick (later).

# tty:

A Pi serial tty device, e.g. /dev/ttyAMA0, /dev/ttyUSB0

## uint32:

An unsigned 32 bit number.

# user\_gpio: 0-31

A Broadcom numbered GPIO.

All the user GPIO are in the range 0-31.

Not all the GPIO within this range are usable, some are reserved for system use.

See gpio.

# wait\_timeout: 0.0 -

The number of seconds to wait in wait for edge before timing out.

# wave\_add\_\*:

One of the following

wave\_add\_new wave\_add\_generic wave\_add\_serial

# wave\_id: >=0

A number referencing a wave created by wave create.

# wave\_send\_\*:

One of the following

wave send once wave send repeat

# wdog\_timeout: 0-60000

Defines a GPIO watchdog timeout in milliseconds. If no level change is detected on the GPIO for timeout millisecond a watchdog timeout report is issued (with level TIMEOUT).

# word\_val: 0-65535

A whole number.

© 2012-2018 e-mail: pigpio @ abyz.me.uk Updated: 20/03/2018